



REPUTE FAQ

HOW TO PERFORM A SILENT INSTALLATION OF REPUTE

The information given here is needed should you want to automatically configure Client Workstations to run Repute on Microsoft Windows Vista, 10, or 11.

Program files

The Repute executable (Repute25.exe), associated libraries (DLLs and BPLs), and other files are installed in one of the following folders:

- 64-bit Windows: C:\Program Files (x86)\Geocentrix\Repute\2.5
- 32-bit Windows: C:\Program Files\Geocentrix\Repute\2.5

Configuration files

Repute's configuration files are installed in the following folder:

- C:\ProgramData\Geocentrix\Repute\2.5

IMPORTANT: The user should have full read/write permissions to the folder above

The following configuration files are used in the normal operation of the program:

- Repute2.lic (licence file, in XML format) – required
- Repute2.cfg (configuration file, in XML format) – optional

Do NOT edit these files except as instructed by Geocentrix Technical Support.

Shared documents

Repute's Tutorials and other shared documents are installed in the following folder:

- C:\Users\Public\Documents\Geocentrix\Repute\2.5

Command line flags for the setup program

To install Repute silently, enter the following command via a command line window:

```
Repute25Setup.exe /s /l="C:\Repute25Setup.log" RUNAPP=FALSE
```

where you can replace "C:\Repute25Setup.log" with a folder and filename of your choosing.

To uninstall Repute silently, enter the following command:

```
Repute25Setup.exe MODIFY=FALSE REMOVE=TRUE UNINSTALL=YES
```

For further information, please contact Geocentrix Technical Support at the email address below.